3wCommunications Hosted Email User Setup Guide Version 1.3

June 8, 2017

Email Client Settings

The recommended incoming protocol to use is IMAP, while POP3 is available we discourage clients using it. Outgoing (SMTP) is available over various ports but we recommend using TLS over port 587 is available. Otherwise SMTP port 465 over SSL and if need be, unencrypted ports are also offered.

Incoming email protocol: IMAP
Outgoing email protocol: SMTP

Secure ports (Recommended)

- IMAP port 993 (SSL)
- POP3 port 995 (SSL)
- SMTP port 587 (TLS) recommended
- Or SMTP port 465 (SSL)

Regular ports (unencrypted)


- IMAP port 143
- POP3 port 110
- SMTP port 25, 587 or 8025

Server Addresses & Logon

- Incoming & Outgoing Mail Server: mail.3wcomm.net
- User Name: Always reflects mailbox / email address

Outlook Setup Example

Replace the E-mail Address username and password with your own account then go to *More Settings...*




More Settings ... / Outgoing Server

Check My outgoing server (SMTP) requires authentication, Same as Incoming.



More Settings ... / Advanced (tab)

Enter the below IMAP (993) and SMTP (587) ports along with SSL / TLS from drop down menus.



Webmail

Secure webmail access is available at the following address: https://mail.3wcomm.net


3w communications		
E-mail address:	e.g. yourname@3wcomm.net	
Password:	password is case-sensitive	
Shared computer:	if checked, you will be logged out after 4 hou	ırs
Stay signed in:	if checked, this browser will log into webmail automatically until you logout	
Login		

Apple iOS Setup


Example of an iPhone running iOS 10 setup for our test domain *zipedit.com*, replace the domain with your own during setup.

Add a New Account on iPhone / iPad


Go to Settings / Mail / Accounts and select Add Account




Select Other from list on screen



Select Add Mail Account under MAIL




Enter Name (Full Name), Email address and Password, Description for this mailbox.



Select **IMAP.** Enter **Incoming & Outgoing** Server Details as shown below.

Username is always your full email address.

When done, click Next.



If any errors appear please double check all spelling, especially Host Names & Passwords.

Select **Mail** on the following screen in regards to what will sync with the server. Click **Save** and you are done.

